

	Airway Doctor 1	Airway Provider 2	Skilled Assistant	Runner
1	Daytime: PACU Faculty Nighttime: On Call Faculty	Daytime: CA-3 Nighttime: CA-3 Mott: CRNA or Fellow	Bedside Nurse and/or Resp Therapist	Primary service team provider (outside of the room UH/CVC) in PPE consisting of N95, glove, MOTT. Tech in gown & disposable eye protection

**Materials to gather and PPE to don before arriving to airway**

2	Equipment: Get code Glidescope GO and Airway Bag. Ensure Airway Bag contains: 7.0 ETT, VL Blades (hyperangulated 3 and MAC 4), disposable Glidescope stylet, standard stylet, Bougie, SGA iGel 4, oral airways, hydrophobic HME filter, lubricant, Clorox wipes, and drug bag. PPE: DON Full water proof gown, N95 Mask and PAPR, goggles, double gloves and a second surgical gown upon arrival to location (within Airway Bag).
---	--

**Airway Management Procedure**

3	<ul style="list-style-type: none"> <li>• <u>Avoid the following unless clinically necessary: CPAP, BIPAP, High-Flow Nasal Oxygen (HFNO), suctioning, and AFOI</u></li> <li>• Ensure a hydrophobic HME filter is between mask and Ambu bag or circuit</li> <li>• Perform pre-procedure timeout (verify roles and induction/airway plan)</li> <li>• Pre-oxygenate for 5 minutes</li> <li>• <u>Rapid Sequence Induction (AVOID BAG MASK VENTILATION unless if clinically necessary)</u></li> <li>• <u>Videolaryngoscopy with GlideScope GO for intubation – Discussion with Team faculty and CA-3 regarding roles and responsibilities</u></li> <li>• Inflate cuff, place HME filter, confirm end tidal CO<sub>2</sub> and hand off to RT to attach to the ventilator to tube with hydrophobic HME filter on tube **If requiring chest compressions with ACLS, stop compressions for intubation</li> </ul>
---	---

**Post Intubation and Equipment Disposal**

4	<ul style="list-style-type: none"> <li>• Dispose of drugs in patient room in sharps container</li> <li>• Remove outer gown and gloves wrapping away from you and include videolaryngoscope blade in disposal pieces.</li> <li>• Wipe GlideScope GO well with Clorox wipes (with clean gloves) ensuring complete coverage and hand to the Runner outside room (both to have Chlorox wipe in hand)</li> <li>• Remove remainder PPE except N95, PAPR Hood, Goggles in room. Be sure to immediately remove protective equipment while keeping sterilization and avoiding self-contamination. Dispose of this into designated garbage to be immediately removed.</li> <li>• Purell on hands and then place another pair of clean gloves outside room</li> <li>• Remove PAPR hood (by disconnecting tubing and pull from back of hood) and throw into garbage immediately outside patient room</li> <li>• Dispose of gloves and wash hands or use Purell</li> <li>• Remove and dispose of goggles and N95</li> <li>• Wash hands again or use Purell and place another pair of gloves</li> <li>• Properly disinfect GlideScope GO Screen Again and then dispose of gloves and wash hands or use Purell</li> <li>• Avoid touching face between steps and be sure to wash hands and/or use an alcohol based prep</li> </ul>
---	--